## **Description of HTTP Output File Formats**

There are two basic file formats that are used for the output of the HTTP trace analysis tools; one that is sorted by TCP connection (output of http\_connect) and one that is sorted by client host (output of http\_active). Both types are text files with very simple fixed-field format where fields are separated by one or more spaces. Each line in a file represents summary information about some "event" that has been extracted from the raw tcpdump traces. Timestamps in these files have the format sssssss.mmmmmmm and are interpreted as fractional seconds with microsecond resolution.

## http\_connect Output Format

The fields in this file in left to right order:

- Timestamp#1 (the meaning is conditional on the value of the Event field as described below)
- Client (browser) IP address
- Client (browser) Port number
- ">"
- Server IP address
- Server Port number":" (the colon is there only for use by some of our tools)
- Event (Event may have one of the following values)
  - "SYN" the normal beginning of a TCP connection; timestamp#1 is the connection start time (timestamp of the SYN packet); timestamp#2 is blank
  - "ACT-REQ" the beginning of a TCP connection where the tcpdump did not contain SYN but the connection was found to have a request in progress; timestamp#1 is the timestamp of the first packet found in the request; timestamp#2 is blank
  - "ACT-RSP" the beginning of a TCP connection where the tcpdump did not contain SYN but the connection was found to have a response in progress; timestamp#1 is the timestamp of the first packet found in the response; timestamp#2 is blank
  - "FIN" the normal end of a TCP connection with a FIN; timestamp#1 is the timestamp of the last packet seen in the connection; timestamp#2 is the connection logical end time (timestamp of the FIN packet)
  - "RST" the normal end of a TCP connection with a Reset; timestamp#1 the timestamp of the last packet seen in the connection; timestamp#2 is the connection logical end time (timestamp of the Reset packet)
  - "TRM" the end of a TCP connection without normal completion (tcpdump did not have a FIN or Reset); timestamp#1 is the timestamp of the last packet seen in the connection; timestamp#2 is the same as timestamp#1
  - "REQ" a browser request; timestamp#1 is the request *start* time (timestamp of first packet containing part of the request); timestamp#2 is the request end time (timestamp of last packet containing part of the request.
  - "RSP" a server response; timestamp#1 is the response *end* time (time of last packet containing part of the request); timestamp#2 is the response start time (timestamp of first packet containing part of the request.
  - "ERR:" an exceptional condition was detected during analysis of the connection; timestamp#1 is the time of the packet where the condition was detected; the last two fields in the line are replaced by a text description of the condition.
- Request or Response size in number of bytes (or blank for other non-error event types)
- Timestamp#2 (the meaning is conditional on the value of the Event field as described above)

NOTE: A sequence of lines with the same values for Client IP address/port and Server IP address/port are all for multiple events from the same TCP connection.

## http active Output Format

The fields in this files in left to right order:

- Timestamp#1 (the meaning is conditional on the value of the Event field as described below)
- Client (browser) IP address
- Client (browser) Port number (or "\*" if no port is associated with the event)
- ">"
- Server IP address (or "\*" if no server is associated with the event)
- Server Port number":" (or "\*" if no server is associated with the event) (the colon is there only for use by some of our tools)
- Event (Event may have one of the following values)
  - "REQ" a browser request
    - timestamp#1 is the request *start* time (timestamp of first packet containing part of the request)
    - timestamp#2 is the request end time (timestamp of last packet containing part of the request)
    - event-data is the request size in number of bytes
  - "RSP" a server response
    - timestamp#1 is the response *end* time (time of last packet containing part of the request)
    - timestamp#2 is the response start time (timestamp of first packet containing part of the request)
    - event-data is the response size in number of bytes
  - "IDLE" a period of time longer than a threshold value (default 2 seconds) no activity by the browsing client because either (a) there were no TCP connections or (b) no existing TCP connection had a request/response exchange in progress
    - timestamp#1 is ending time of the idle period
    - timestamp#2 is the beginning time of the idle period
    - event-data is the elapsed time of the idle period in milliseconds.
  - "ERR:" (or "ERROR") an exceptional condition was detected during analysis of the connection; timestamp#1 is the time of the packet where the condition was detected; the last two fields in the line are replaced by a text description of the condition.
- Event-Data (the meaning is conditional on the value of the Event field as described above)
- Timestamp#2 (the meaning is conditional on the value of the Event field as described above)

NOTE: A sequence of lines with the same value for Client IP Address are all for multiple events from the same browsing client.